



Version 4.0 Setup Update Checking

To check for updates, please do the following.

1. Run command: ADDLIBLE #MENUi4

```
90. Sign off

Selection or command
==> addlible #MENUi4

F3=Exit   F4=Prompt   F9=Retrieve   F12=Cancel   F13=Information Assistant
F23=Set initial menu
(C) COPYRIGHT IBM CORP. 1980, 2009.
```

2. Run command: MENUi *ADMIN and press **ENTER**. Page down and select the “Destination Maintenance” option.

```
MMADMIN                T E S T   C O M P A N Y                08/02/18
INV 1                  A D M I N I S T R A T O R   M E N U                QPADEV0006
*LIVE                  C u r r e n t   R e l e a s e   4 . 0 . 0 0 0                *ADMIN
-----
29. Notification Maintenance                41. Cleanup Job Library List Entries
30. Notificaton Driver Maintenance          42. Rebuild Logging Definitions
                                           43. Rebuild System Function Keys

LOGGING:
31. Menu Item Run Log                       UPDATE:
32. Menu Change Log                         44. Destination Maintenance
33. Extract Menu Log Data                   45. Update Manager
34. Extract Menu Change Log Data
35. Delete Menu Change Log Data
36. Delete Menu Log Data
37. Delete Menu Stat Log Data
38. Delete Notification Log Data

GENERAL:
39. Special Value Passing File Clean
40. User Job Cleanup

Option:           
F2=Change Group   F3=Exit   F12=Previous   F16=Search

Bottom
```



Version 4.0 Setup Update Checking

3. Press **F6** to add a new entry. Type the following values and press **Enter**.

```
ALAM147R/SCR02          MENUi - Menu          18/08/02
                        Destination Maintenance - Update  QPADEV0006
                                                                MENUi

Connection Type.....: *FTP

Destination ID.....: RLS_DL
Description.....: Release download

Name or Address.....: FTP.FOURSQUARES.CA

User Name.....: release@foursquares.ca
Password.....: release2018!
Account.....: _____

F3=Exit  F12=Previous
```

This will allow you to check for updates.



Version 4.0 Setup Update Checking

4. Press **F6** to add a new entry. Type the following values along with your username and password, and press **Enter**. If you do not have a user name and password, please contact us to obtain your username and password.

```
ALAM147R/SCR02          MENUi - Menu          18/08/02
                        Destination Maintenance - Update  QPADEV0006
                                                                MENUi

Connection Type.....: *FTP

Destination ID.....: UPD_DL
Description.....: Update download credentials
Name or Address.....: FTP.FOURSQUARES.CA

-----

User Name.....: _____
Password.....: _____
Account.....: _____

F3=Exit  F12=Previous
```

This will allow you to download updates.



Version 4.0 Setup Update Checking

- 5. Confirm constants are setup correctly. Run command: MENUi *ADMIN and press **ENTER**. Select the "Constant Maintenance" option.

```
MMADMIN          T E S T   C O M P A N Y          08/02/18
INV 1            A D M I N I S T R A T O R   M E N U      QPADEV0006
*LIVE           Current Release 4.0.000                *ADMIN
=====
  1. Environment Maintenance          17. Item Run Maintenance
  2. Group Maintenance               18. View User Menu
  3. Menu Item Maintenance           19. Find Menu Path
  4. Menu Maintenance                20. Find Item Use
  5. User's Initial Menu Maintenance 21. Environment Assignment Mainten
  6. Item Forced Option Maintenance  22. User Group Assignment Maintenance
  7. Item Attribute Maintenance      23. User View Assignment Maintenance
  8. Menu Item Confirm Maintenance
  9. Special Value Maintenance
 10. Constant Maintenance
 11. Menu Item Lock Maintenance
 12. Menu Library Maintenance
 13. Item Group Maintenance
 14. Menu Item Sequence Maintenance
 15. Call Statistics Maintenance
 16. Active Users
                                     SECURITY:
                                     24. Menu Item Security Maintenance
                                     25. Menu Item Job Security Mainten
                                     26. Check User Menu Access
                                     27. User Menu Access
                                     28. Exit Point Maintenance
                                     NOTIFICATION:
                                     90. Sign Off
                                     More...

Option: █
F2=Change Group  F3=Exit  F12=Previous  F16=Search
```



Version 4.0 Setup Update Checking

- Update the update and download constants accordingly. The release constant should have a value of *RLS_DL*.

```
ALAM117R/SFL01          MENUi - Menu          18/08/02
                        Constant Maintenance    QPADEV0006
                                                MENUi

Type option, press Enter.
  2=Change  4=Delete  6=Send To Environment

Opt  Key                Sub Key                Constant Value
-----
  █  ##MENSEPR           =
  _  ##OPTNFULL          Y
  _  ##OPTNSEPR          .
  _  ##OPTNVCHG          Y
  _  ##OPTRUNSEQMKR     *RIGHT
  _  ##PASSWORD         MMADMIN *MENU          *GROUP:INTMENSEC, *SPECIAL:<|
  _  ##PRIORCMD          Y
  _  ##PRODUCTID        *MENUi
  _  ##RLSDST           RLS_DL
  _  ##SBOPTN           Y
  _  ##SHNONCALLO      N
  _  ##SHWFRCOPT       Y

More...

F3=Exit  F6=Add  F11=Change View  F12=Previous  F16=Search
```



Version 4.0 Setup Update Checking

The download constant should have a value of *UPD_DL*.

```
ALAM117R/SFL01          MENUi - Menu          18/08/02
                        Constant Maintenance    QPADEV0006
                                                MENUi

Type option, press Enter.
  2=Change  4=Delete  6=Send To Environment

Opt  Key                Sub Key                Constant Value
-----
  █  ##SVIGNMSG          CPF3701
  -   ##TMPFLDR          /HOME/
  -   ##UPDDST           UPD_DL
  -   ##UPDSFKEY         N
  -   ##USERHELP         N

Bottom

F3=Exit  F6=Add  F11=Change View  F12=Previous  F16=Search
```